



Radiation Belt Environment Quick Start Guide



-
- cd to <your software installation directory>/scripts and edit RBE_end_to_end.pl
The \$BASEDIR variable must be set to the software installation directory.
 - rbe_init.txt can be found in: <your software installation directory>/setup
The parameters listed below must be changed in rbe_init.txt. For a more complete description of these parameters please see section 3.1 of the *RBE User's Guide*.

mag_datadir = Location of the magnetometer data files
image_dir = Location of the RBE output .png files

- The file *.netrc* must reside in the user's home directory and be accessible only by the user. For details about the *.netrc* file, see Radiation Belt Environment User's Guide Section 3.1. (**Note: the permissions on the *.netrc* file must be set owner read, write, execute only. This can be done by issuing the following command: `chmod 700 .netrc`**)
- Cd to <your software installation directory>/scripts and edit run_plotting_tools.pl.
LD_LIBRARY_PATH should be changed to match your UNIX environment.